# Facial Recognition Server Software WV-ASF950 Series Instructions how to upgrade from V3.xx to V4.xx

This tool can upgrade in both function (registered face detection or registered face/unregistered face detection)

In this system, based on the verification results in various environments, the initial value of alarm sensitivity in face registration is defined as "1.04".

This alarm sensitivity depends on environment and registered face image, so adjust the alarm sensitivity on site from the initial value "1.04".

The recommended alarm sensitivity is "1.12" because false alarms tend to increase in environments where there are many face images wearing face mask on both registered and detected faces.

If you use V1.xx or V2.xx, you cannot update directly to V4.xx. First, update to V3.20 using "UpdateTool\_for\_ASF950\_V1\_V2\_to\_V3\_20", and then use "UpdateTool\_for\_ASF950\_V3\_xx\_to\_V4\_xx to update to V4.xx."

After uninstalling the previous version of WV-ASF950, a message to restart PC may be displayed, but please proceed according to the display of the UpdateTool without restarting.

install:	owing applications s	hould be close	d before continuin	g the
ASF95	50ShutdownMonitor	exe		
● Auto setu	omatically close appl p is complete.	ications and att	empt to restart the	m after
	not close application	s. (A Reboot ma	y be required.)	

Contact the system administrator or your dealer for further information when the following message is shown "PostgreSQL is not running" or "MDDB backup error" or "Configuration file is not found".

ASF950 Software Update	×	ASF950 Software Update
PostgreSQL is not runnning!	MDDB backup error.	Configuration file is not found.
ОК	ОК	ок

# Outline

The upgrade uses the tools as follow;

- ConfigTool : WV-ASF950 ConfigurationTool (Shortcut on desktop)
- Update tool: UpdateTool\_for\_ASF950\_V3\_xx\_to\_V4\_xx
  - \* Check version file by using notepad, etc. ("C:\ASF900\version")

\* Do not execute each tool directly from USB memory, etc. Please execute after copying to a local disk such as the Desktop.

Procedure outline:

No	Procedure	Contents	Tool for use
1	Stop the system	Stop the system, and confirm the server type is master or slave server	Config tool
2	Update the system	Copy new files and update system information	Update tool
3	Start the system	Confirm system version and start the system	Config tool
4	Adjust alarm sensitivity	djust alarm sensitivity Adjust alarm sensitivity on site for each environment.	
5	Update camera information	Updates the camera information to detect face mask	Config tool

Also, install the Error Notification Tool on any PC to check the server operation status.

\* it is necessary to uninstall the existing Error Notification Tool. The registered server information will remain after uninstallation, so not need to register the server again after installing the latest version.

Procedure outline:

No	Procedure	Contents
1	Uninstall	Uninstall the previous version of the Error Notification Tool.
2	Install	Install the Error Notification Tool on any PC.
3	Register server	Register the server in the Error Notification Tool.

# Update server software on each server PC.



### 1. Stop the system

- (1) Run "WV-ASF950 Configuration Tool" and click "Process Control" tab.
- (2) Check whether the server type is master server or slave server."Not Installed" is shown in the rectangle (2) of following figure, this is slave server.Otherwise this is master server.(The following figure is a sample of master server)
- (3) Make sure "All Process" is selected, then click "Stop" button.

🛃 WV-ASF950 Configuration Tool			- 🗆 X
WV-ASF950 Configuration Tool Server Configuration Server Settings Secure Settings	(ASF990ConfigTool Ver. 10.023) icense Managemen Process Control (1)	English	Exit
Process Control Refresh			
Start	<sub>Stop</sub> (3)		
All Process			
ASF950BRK01	Running (2)		
■ ASF950BRK03	Running		
ASF950BrokerManager	Running		
ASF950httpd	Running		
ASF950Redis	Running		
ASF950MSM	Running		
ASF950EXT01	Running		
ASF950EXT06	Running		

(4) Make sure all processes are "Stopped", then click "Exit" button.



## 2. Update the system

Contig is a defragmentation tool provided by Microsoft. Confirm that Contig is already installed in the following folder "C:\Contig\Contig64.exe"

If Contig is already installed, execute the procedure (1). If not, download Contig from the following URL on the PC that can connect to the Internet. Note) Use Contig version 1.8.0.0 or later.

URL: https://docs.microsoft.com/en-us/sysinternals/downloads/contig

Note) If the following screen appears when you right-click Contig.zip and open the properties screen, check "Unblock" and click "OK" to unzip it.

ieneral Secu	unity Details Previous Versions					
(L'source	Contig.zip					
Type of file:	Compressed (zipped) Folder (.zip)					
Opens with:	Hindows Explorer Change					
Location:	C:\Users\Desktop					
Size:	241 KB (246,787 bytes)					
Size on <mark>dis</mark> k:	244 KB (249,856 bytes)					
Created:	Today, March 4, 2020, 1 minute ago					
Modified:	Today, March 4, 2020, 53 minutes ago					
Accessed:	Today, March 4, 2020, 1 minute ago					
Attributes:	Read-only Hidden Advanced					
Security:	This file came from another computer and might be blocked to help protect this computer.					

Download and unzip the Contig.zip to "C:\Contig\Contig64.exe" on the server.

Note) There is no need to run Contig64.exe. After updating by the update tool, it will be executed automatically every Monday at 4:00. This tool is required for optimal defragmentation, and WV-ASF950 cannot be updated without Contig.

Execute Copy new files and update system information by update tool.

- (1) Run "ASF950UpdateTool.exe" in the folders of "UpdateTool\_for\_ASF950\_V3\_xx\_to\_V4\_xx\04\_Tools" folder.
  - \* Please execute after copying to a local disk such as the Desktop

Contact the system administrator or your dealer for further information when the following message is shown "PostgreSQL is not running" or "MDDB backup error" or "Configuration file is not found".



(2) Enter / confirm the database password



The password for the database that has already been set will be displayed. Confirm that the password is correct.

(3) Graphic board Select displays a list of GPUs used by the server.If the driver is not supported, a [Cancel] button with a warning will be displayed.

ASF950 Software Update	- 🗆 X
Update Procedure	ASF950 Database password
STEP1 Set DB password STEP2 Uninstall old Software	Please enter the Database password OK Please enter a password to protect your data, and manage it so that you do not forget it.
Install new Software	Graphic board Select The graphic board was not found! Please by again after installing the graphic board.
	Cancel

After updating the driver version to 471.68 or higher, start the advanced tool again.

(4) Click "Next" button



(5) The uninstall window is displayed.



Uninstall "WV-ASF950 V3.xx" from "Programs and Features" of the control panel.



After uninstalling the previous version of WV-ASF950, a message to restart PC may be displayed, but please proceed according to the display of the UpdateTool without restarting.

The following app install:	plications should be closed before continuing the
ASF950Shutdov	wnMonitor.exe
Automatically	close applications and attempt to restart them after
<ul> <li>Automatically setup is comp</li> </ul>	close applications and attempt to restart them after lete.
Automatically setup is comp	close applications and attempt to restart them afte lete.
Automatically setup is comp     Do not close a	close applications and attempt to restart them after lete. applications. (A Reboot may be required.)

(6) After uninstalling, click the Next button.



(7) Put a check mark on "I accept the terms in the License Agreement" and then click the [Install] button.



(8) Click the [Finish] button to complete the installation.



(9) Installation and configuration of the new software will begin.

When "Install Completed" is displayed and the installation is completed, click the Finish button to finish the upgrade.



(10)Follow the instructions in the dialog to restart server PC.





# 3. Start the system

- (1) Run "WV-ASF950 Configuration Tool"
- (2) Check that config tool version is "V4.xx.x.xxxx". And check that server version is "V4.xx"

#### [Master server]

1. Check the Broker server version.

WV-ASF950 Configuration Tool							×
WV-ASF950 Configuration Tool	F950ConfigTi	ool Ver. 3.00 )		Engl	lish	Ex	it
Server Configuration Server Settings Secure Settings License I	Managem	ent Process C					
Broker Node 192.168.0.215							
Broker (192.168.0215)         Refresh           Carn1 (192.168.0.104)         Carn2 (192.168.0.104)           Carn2 (192.168.0.163)         Carn2 (192.168.0.106)           Carn2 (192.168.0.106)         Carn2 (192.168.0.107)           Carnal (192.168.0.107)         Carnal (192.168.0.107)	Node E No IP Po Ma Noc	Information dit Address rt No. AC Address Re List Entry: 2	Broker 192.168.0.215 80 18.60.24:87:9A:1F amera List		(v3.:1)	)	
	No.	Server ID	Node No.	Node type	IP Address	Port	No.
	01	2	1	Face Matching Node Face Matching Node	192.168.0.215	80	

2. Check the Face Matching server (FM1) version.



#### [Slave server]

Check the Face Matching server (FM2 or later) version.



(3) Run "WV-ASF950 Configuration Tool" and click "Process Control" tab. Make sure all processes are "Running", then click "Exit" button.



# 4. Adjust alarm sensitivity

In this system, based on the verification results in various environments, the initial value of alarm sensitivity in face registration is defined as "1.04".

This alarm sensitivity depends on environment and registered face image, so adjust the alarm sensitivity on site from the initial value "1.04".

The recommended alarm sensitivity is "1.12" because false alarms tend to increase in environments where there are many face images wearing face mask on both registered and detected faces.

Recommended alarm sensitivity

	Detected face image				
Registered face image	without face mask	with face mask			
without face mask	1.04	1.04			
with face mask	1.04	<u>1.12</u>			

#### 4.1. Select registered person and adjust alarm sensitivity

(1) Click "Face Management" button on the lower left of the face search monitor of client software.



(2) The "List of registered faces" window will be displayed.Select a registered face image from the list, and then click the [Change] button.



(3) The "Select and register face image from snapshot." window will be displayed.Set the alarm sensitivity to "1.12" using the up/down buttons or slider, and click "OK" button.

Select and re	ister face	e image from snapshut					×
(	)	Toget The regressentative face image a six a regretated image youch at an face search scoren.	il te displayed alarm of the	Select file. Detected face is shown with Select the face set an illinois The face without white from in this case, select another o	white frame, glown a lower right face. Shown a t has not detected as face, agestock.	d list.	
O	¢	Rejectered law image last					
None			*				
Neg.			-				
Gender		Man     Worsen	O Arbitrary				
Remarks							
Cutrgory							
	10						
Alarro sensitivity	1.						11
Validity period							
Select ann		Select area	registreton.				
Clear						OC Cancel	1

# 4.2. Adjust alarm sensitivity to [1.12] by batch file

It is to change alarm sensitivity to [1.12] by batch file. This batch will not change for persons whose alarm sensitivity is already set higher than 1.12.

(1) Copy batch file on desktop of master server.

Double click this batch file, and input y/Y button + ENTER key. And input database password + ENTER key.



(2) When the batch process completes successfully, the message below is displayed. 20 items will be reflected in the operational status each 10 seconds.



(3) If an error occurs, a message will be displayed.Check the database password and execute the batch file again.



#### 4.3. Change the initial value for new registrations

When registering a new face for alarm notification, the initial value of the alarm sensitivity can be set to a pre-determined value.

- (1) Finish client software.
- (2) Open "C:\Program Files (x86)\i-PRO\asm300\aplxml" folder \*In case of WV-ASM300
   \* "C:\Program Files\i-PRO\asm300\aplxml" in Windows 32bit edition.
   Copy "constants.xml" file on desktop.

(3) Open and edit constants.xml by notepad

<constant name="AlarmSensitivity" value="1.04" />

Save and copy constants.xml in "C:\Program Files (x86)\i-PRO\asm300\aplxml" folder.

(4) Start client software, and click "Face Management" button on the lower left of the face search monitor.



(5) The "List of registered faces" window will be displayed. Click the [New registration] button.



(6) The "Select and register face image from snapshot." window will be displayed. Check the initial value of the alarm sensitivity is the value you have set.





# 5. Update camera information

When using the face mask detection function of the camera (supported cameras only in i-PRO EXTREME series), it is necessary to update the camera information afar camera firmware is updated in V2.00 or later.

- (1) Run "WV-ASF950 Configuration Tool" on master server.
- (2) Select "Server Configuration" tab.

Select camera in device tree for updating information and click "Edit" button.



Camera setting window is shown.

(3) Click "Connect" button.

"Connected" is shown, and configuration tool connects the camera and gets camera information.



Face Mask Detection menu is shown. Select Face Mask Detection level in pull-down menu.

\* High level is recommended.

And Click "Update and Close" button.



- (4) Repeat steps (2)-(3) for other cameras as well.
- (5) On "Process Control" tab, stop all processes and start them again in order to reflect the setting.



(6) If there is **another slave server**, stop all processes and start them again.

# Update Error Notification Tool on the client PC on which this tool is installed.



# 1. Uninstall

Execute this step only when there is a previous version of the Error Notification Tool (Version 3.xx).

(1) Right-click the icon displayed in the lower right corner of the Desktop, click "Exit", and click "Yes" on the exit confirmation message to exit the tool.



- (2) Select [Control Panel]-[Uninstall a program] or [Programs and Features].
- (3) Select "WV-ASF950 Error Notification Tool" from the programs displayed in the [Uninstall or change a program] window, and click the "Uninstall" button.
- (4) Follow the on-screen instructions to uninstall.
  - \* Not need to restart the PC after uninstalling.



## 2. Install

- (5) Copy the "UpdateTool\_for\_ASF950\_V3\_xx\_to\_V4\_xx \Error Notification Tool" folder to the PC which is registered as terminal in WV-ASF950 Configuration Tool.
- (6) Execute "WV-ASF950\_Error\_Notification\_Tool\_Setup\_vnnnn.exe" in the "Error Notification Tool" folder.
  - \* nnnn contains version information.

\* Choose the installer as your preferred display language. (vnnnn.exe: English version, vnnnnJ.exe: Japanese version.)

(7) Click "Next >" button.



(8) Select "I accept the terms in the license agreement" and click "Next >" button.



(9) Installation of the Error Notification Tool starts. When the installation is completed, click the "Finish" button to finish.





# 3. Register server

Perform this procedure when performing a new installation (less than version 2.00) or when changing the system configuration.

\* The registered server information will remain after uninstallation, so not need to register the server again after installing the latest version.

- (1) Double-click "WV-ASF950 Error Notification Tool" on the Desktop to start.
  - \* It does not start automatically, so please execute the tool from the shortcut after installation.
- (2) Right-click the icon displayed in the task tray and click "Open Information". The Error Notification Tool window will be displayed.



(3) Click "Add" button.

Server Registration window will be displayed.

ASF Series	Face Server I	nformation	
Add	Edit	Delete	Close

(4) Enter the IP address.

If SSL is on for the server, check "SSL". Make sure that "Master" is checked at the server type. After setting, click "Add" button.

		×		
ASF Server Registration				
IP Address	192.168.0.209			
Port No.	80 🔳 SSL			
Server Kind	• Master			
<u> </u>	Add			

Confirm that the registered master server is added to the Error Notification Tool window and "Status [OK]" is displayed.

		×		
ASF Series Face Server Information				
Master [192.168.0.209]	Status[OK]			
Add Edit D	elete Clo	se		

If the status does not change to "OK", please check that the IP address is correct and there is no problem with the network device, and that the service process of the facial recognition server is running.

(5) If there is another master server or slave server, add the server by following steps (3)-(4). To add a slave server, select the master server and click the "Add" button.