Notes on upgrading the Extension Software, WV-SAE200 TYPE3 for WV-SFV481/SFN480

This document describes important notes while using the cameras with the software as follow;

Cameras

WV-SFV481 and WV-SFN480

Software

Extension Software, WV-SAE200 TYPE3 (Not included WV-SAE200 TYPE1/TYPE2)

The table shows recommended combination between firmware version on camera and software version.

1000

Notes:

*: It works but recommend to upgrade latest ver.

**: It might not work depends on configurations.

| | | Extension Software WV-SAE200 TYPE3 | | |
|-----------------|--------------|------------------------------------|---------------------------------|--------------------------|
| | | V1.03 | V1.05 | V1.20 |
| | | (1 st release) | (2 nd release) | (New) |
| | V1.02 | Incompatible | Incompatible | Incompatible |
| 0 | V1.11 | Yes (Recommended) | No ** (Not recommended) | ×** (Not recommended) |
| ion FN48 | V1.12 | Yes * | Yes (Recommended) | ×** (Not recommended) |
| e vers 181/S | V1.13 | Yes * | Yes (Recommended) | ×** (Not recommended) |
| nware -SFV | V1.14 | Yes * | * Yes (Recommended) (Not rec | ×** (Not recommended) |
| Firr or WV | V1.15 | Yes * | Yes (Recommended) | ×** (Not recommended) |
| Ę | V2.01 | ×** (Not recommended) | ×** (Not recommended) | ×** (Not recommended) |
| | V2.02 | ×** (Not recommended) | ×** (Not recommended) | Yes (Recommended) |

Procedures how to upgrade (From V1.xx)

page **3**/6

Procedures how to upgrade

When upgrading the Extension software WV-SAE200 TYPE3 version 1.20 and WV-SFV481/SFN480 firmware from version 1.xx to 2.01 or later, in a case the Extension software WV-SAE200 TYPE3 (V1.03 or 1.05) has been installed.
!!!Note!!! Do not change configuration setting while in the STEP 1 to STEP3. Or, it may be a cause of failure.



STEP2 Uninstall the Extension Software version 1.20

| CTED2 | Upgrade camera firmware to version 9.99, |
|-------|--|
| SIEP3 | then upgrade firmware version 2.02. |

STEP4 Restore the following configuration settings on camera Alarm type should be selected to "i-VMD". Make the Schedule settings for i-VMD if necessary.

Procedures how to upgrade (From V2.xx)

page 4/6

Procedures how to upgrade

When upgrading the Extension software WV-SAE200 TYPE3 version 1.20 and WV-SFV481/SFN480 firmware from version 2.01 to 2.01 or later, in a case the Extension software WV-SAE200 TYPE3 (V1.03 or 1.05) has been installed.
IIINote!!! Do not change configuration setting while in the STEP 1 to STEP3. Or, it may be a cause of failure.



STEP2 Uninstall the Extension Software version 1.20

STEP3 Upgrade camera firmware to version 2.02.

STEP4 Restore the following configuration settings on camera Alarm type should be selected to "i-VMD". Make the Schedule settings for i-VMD if necessary.

For your references

How to make sure the firmware version You can see the firmware version by following procedure.

| Ext. software | | |
|---|------------------------------|---|
| Unique information | | |
| MPR ID | 5405-0105-4000-000 | |
| Remaining ROM | 3996 kbytes | Use this button at |
| Remaining RAM | 1048 kbytes | the STEP1 |
| i-VMD / Face detection | | |
| oftware version | 1.00 | |
| Status | 1012-035-1755-043 | |
| Setup menu | Setup >> | |
| ● Install new Ext. s ○ i-VMD / Face de | software etection Upgrave | Execute DO NOT USE this a the STPF1 |
| Please wait and do | not operate the browser di | |

For your references

Alarm (Firmware V2.02 (and newer), Extension software V1.20 (and newer) "VMD" will be selected automatically if it were inappropriate combination.

